

Speos 安装教程

新科益系统与咨询(上海)有限公司



目录

1.软件安装前准备

2.服务端license manager安装

3.Speos 安装

4.设置客户端license选项

软件安装前的准备

安装前更改电脑基本设置

1.关闭防火墙




2.关闭杀毒软件

3.使用管理员身份


4.确认1055或2325端口打开

服务端License Manager安装


以管理员身份运行setup




点击Install ANSYS License Manager①




按照箭头操作




指定license manager安装路径




点击Next, Next, Next



等待安装完成，点击Exit



在弹出的网格管理器界面中进行许可的加载



检查License管理软件在服务器端是否运行正常

Ansys

✓ Ansys License Manager Release 2021 R2

Home

View Status/Start/Stop License Manager
Reread License Manager Settings

License File Options

Add a License File
Get System HostId Information
View FlexNet Licenses

Log Files

View Licensing Interconnect Log
View FlexNet Debug Log
View License Management Center Log

Reporting

View Current License Usage
View License Usage History
View Peak License Usage
View License Denials

Diagnostics

Display FlexNet License Status
Gather Diagnostic Information
Display Queued Licenses

Advanced Options

Specify License Manager Run Mode

Help

View ANSYS Licensing Guide
View FlexNet Licensing Guide


✓ The license manager is running. STOP

Licensing Interconnect: running
Licensing Interconnect Monitor: running
FlexNet Licensing: running


要保证三个都是“running”

软件安装


点击Install ANSYS Products②




按照箭头操作




选择文件安装路径




客户端输入主机名 服务端跳过



选择optical




等待安装




设置客户端License选项

管理员身份打开Ansys Client Licensing Settings 2021R2



Port端口为1055, Server1为服务器的主机名或IP地址, 点击Test, Save



显示客户端license状态

The screenshot shows the 'Client Settings Utility' interface for 'Ansys Licensing Client Settings 2021 R2'. The main heading is 'Reporting > FlexNet Publisher License Status'. On the left, a navigation menu includes 'License Servers', 'Reporting', 'User Preferences', 'Borrow', and 'Gather Diagnostics'. A red arrow points to the 'FlexNet Publisher License Status' link under the 'Reporting' section. The main content area displays a list of license users and their status:

- Users of afsp_fensapice_cfd: (Total of 2 licenses issued; Total of 0 licenses in use)
- Users of afsp_gui: (Total of 2 licenses issued; Total of 0 licenses in use)
- Users of afsp_optigrid: (Total of 2 licenses issued; Total of 0 licenses in use)
- Users of afsp_viewmerical: (Total of 2 licenses issued; Total of 0 licenses in use)
- Users of aim_mp1: (Total of 2 licenses issued; Total of 0 licenses in use)
- Users of ane3: (Total of 1 license issued; Total of 0 licenses in use)
- Users of ans_act: (Total of 1 license issued; Total of 0 licenses in use)
- Users of ansys: (Total of 2 licenses issued; Total of 0 licenses in use)
- Users of aqwa_pre: (Total of 2 licenses issued; Total of 0 licenses in use)
- Users of aqwa_solve: (Total of 2 licenses issued; Total of 0 licenses in use)
- Users of cae4abaqus: (Total of 1 license issued; Total of 0 licenses in use)
- Users of cae4nastran: (Total of 1 license issued; Total of 0 licenses in use)
- Users of cae4samcef: (Total of 1 license issued; Total of 0 licenses in use)



新科益工程仿真中心

咨询邮箱：ansysupport@cadit.com.cn

公司网址：<http://www.cadit.com.cn>